
The Applicability of Sample Collection and Analysis in Support of Nuclear Arms Control Agreements

Raymond R. McGuire

August 1, 1995



DISCLAIMER

This document was prepared as an account of work sponsored by an agency of the United States Government. Neither the United States Government nor the University of California nor any of their employees, makes any warranty, express or implied, or assumes any legal liability or responsibility for the accuracy, completeness, or usefulness of any information, apparatus, product, or process disclosed, or represents that its use would not infringe privately owned rights. Reference herein to any specific commercial product, process, or service by trade name, trademark, manufacturer, or otherwise, does not necessarily constitute or imply its endorsement, recommendation, or favoring by the United States Government or the University of California. The views and opinions of authors expressed herein do not necessarily state or reflect those of the United States Government or the University of California, and shall not be used for advertising or product endorsement purposes.

This report has been reproduced directly from the best available copy.

Available to DOE and DOE contractors from the Office of Scientific and Technical Information P.O. Box 62, Oak Ridge, TN 37831 Prices available from (615) 576-8401, FTS 626-8401

Available to the public from the National Technical Information Service U.S. Department of Commerce 5285 Port Royal Rd., Springfield, VA 22161

THE APPLICABILITY OF SAMPLE COLLECTION AND ANALYSIS IN SUPPORT OF NUCLEAR ARMS CONTROL AGREEMENTS

Raymond R. McGuire

Arms Control and Treaty verification Program
Lawrence Livermore National Laboratory

Introduction:

Agreements are being negotiated to halt the spread of nuclear arms both within the declared nuclear weapons states and to states not heretofore declaring their possession. With the verification regime of the recently negotiated Chemical Weapons Convention (CWC) as a model, negotiators are considering variations of on-site inspection as formulas to enhance the assurance of compliance with future agreements. These on-site inspections may be part of a treaty dictated verification regime or one of a set of voluntary "confidence building" measures. In either case, the collection of material samples for analysis could be an integral component of the inspection as it is in the CWC. The following is an assessment of the applicability of sampling and analysis for compliance monitoring nuclear arms control agreements currently envisioned.

There are two essentially orthogonal ways of approaching this question of applicability: the consideration of the analytical questions and the consideration of the specifics of the individual agreements. This study is meant to utilize both approaches in examining the possible impact of sampling and analysis on compliance assessment.

First attention must be given to technical questions relating to the efficacy of sampling and analysis.

Effectiveness of Sampling and Analysis:

1. Can Relevant Samples Be Obtained?

One of the most important aspects of sampling and analysis for compliance information is the collection of samples that contain the necessary analytes in quantifiable concentrations. This ability to quantify is more important in cases where a detectable amount of an analyte is always expected. This aspect differentiates analysis for nuclear agreements from analysis for CW or BW agreements where the mere detection of certain materials raises a compliance concern. Questions of sample homogeneity are also heightened.

The kinds of samples that may be required are varied. They include the following.

- a. Process samples These may be solids (powdered metals or metal oxides, or even solid bits of metal), liquids (aqueous solutions, organic liquids, etc.), or vapor or particulates trapped on adsorbents. They may also be samples collected on wipe of process equipment or nearby surfaces.
- b. Product samples These samples are more likely to be solids from surface scrapings or wipes of surfaces. They may also include gaseous samples if materials like UF_6 are considered to be products.
- c. Stockpile samples The types of materials included here are identical with those listed under product samples. However, since further "packaging" may well have taken place, the samples could be significantly less accessible.
- d. Waste samples All waste streams, when they are fresh, contain the same elemental and molecular species as the process streams even though the relative concentrations of components will vary dramatically. (Since reactions may continue in waste streams, the molecular identity of constituents may change with time). The types of samples to be collected are similar to process samples.
- e. Environmental samples Environmental samples arise from the ancillary spread of material during production, storage or use. The analytes of interest are usually dissolved in or adsorbed on other media. Such media include water, soil and other adsorptive surfaces such as vegetation and filters. Atmospheric samples also fall into this category. Analyte concentrations and be significant if the samples are collected from closed vessels such as a storage container of the cavity resulting from an underground explosion.
- f. Reference Standard samples Since quantification is of such importance when dealing with nuclear issues, the acquisition of reference standards for comparison of signal amplitude becomes critical. Standards may need to be artificially prepared for certain materials to mimic sample aging.

2. Can Significant Analyses Be Performed?

In order to obtain consequential results from an analysis, the measurement technology must be well characterized and reliable. (Most of the procedures that would be applied for this purpose are well characterized and reliable). Moreover, many samples must be separated into sub components and/or concentrated prior to the measurement. (Many of these sample preparation procedures are not so well characterized or reliable). Some of the considerations relating to sample analyses are as follows.

- a. Sensitivity / Resolution of analytical measurements Since many of the important analytes may be present in only trace amounts, very sensitive techniques will be needed to obtain a signal to noise ratio sufficient for quantification. In addition, the technique must be capable of distinguishing between analytes having similar or nearly identical properties; e.g., two ions of the same mass number. Thus very high resolution will be needed in certain instances.
- b. Accuracy of measurements Obtaining accurate measures of concentration is complicated by the ability of the analyst to separate a component into an analyzable form (sample preparation) and by the fact that instrument response may not be linear over the necessary range of concentration. It is necessary to characterize the error in accuracy of the entire procedure (sample preparation and measurement) over the expected range of concentrations.
- c. Reproducibility of measurements Analytical data must be reproducible from day to day and from sample to sample. This requires that the instrumentation be well maintained and precisely calibrated. In addition, any sample preparation procedure must be well characterized and rigidly followed.
- d. Isotopic ratios The analytical requirements (a, b, and c above) may not be quite so demanding at all times. In some cases it will be satisfactory to obtain the ratio of the analyte of interest to a second analyte in the sample. For example the ratio of 235 U to 238 U may be adequate, rather than having to attempt to measure the absolute concentration of 235 U. In this case, the 238 U becomes a sort of "internal standard" for the analysis. Similar use of ratios of analytes may be extended to organic analysis.
- e. Absolute quantification In some cases it will be necessary to precisely measure the amount of analyte. This may be accomplished by a number of techniques. However, all of the techniques require that any sample preparation procedure be well characterized and rigorously followed and that the analytical measurement be carefully maintained, calibrated and operated. Reference standards will be required for instrument calibration and / or use as a quantification standard depending on the methodology selected.
- f. Trace analysis It may be necessary to quantitatively measure materials that are present in very low concentrations. As stated above, this will place a premium on the sensitivity of the instrumental method and on the capability of the analyst. In most cases, the concentration required for quantification is significantly higher than that needed for detection. Analysis of radioactive materials can be performed with good accuracy at lower concentrations and with smaller samples, if no preparation is necessary, than can the analysis of non radioactive materials.
- g. "Hot" samples Materials that are intrinsically radioactive or in which radioactivity can be induced, can be analyzed at lower concentrations and with smaller samples than non radioactive materials. However, handling radioactive samples presents other problems; particularly related to waste disposal, decontamination of equipment and safety. The analysis of radioactive and non radioactive materials will probably not performed on the same instruments or in the same laboratory, even if the same analytical technique is used for both types of materials. Special measures will be needed to ensure that the measurements are comparable.
- h. Non radioactive analytes Key analytes may be either organic or inorganic, non radioactive materials. In many cases it will be necessary to perform extensive sample preparation to isolate and concentrate these analytes. Since no sample preparation method is 100% effective, the technique selected will have to be well characterized and reproducibly followed so that comparable results are obtained with each application.

3. Can Meaningful Interpretations Of The Data Be Made?

Given that samples have been properly collected and that the analyses have been performed with the best available technology, there remains the question of whether the results can be interpreted meaningfully. It will be rare that the analytical evidence will be so powerful that it will point unambiguously to compliance or non compliance. It is more likely that the data will be consistent with either compliance or non compliance and conflict with the alternative. Thus the data will be indicative rather than absolute.

A very important question while interpreting the data is one of kinetics. It may be possible to effectively "date" the event that gives rise to the detected analyte and it will frequently be critical to do so. Whether the data indicates an ongoing activity or one that was terminated at some time in the past is a very important distinction to be made in the arms control arena.

Finally, since certain nuclear activities will legitimately continue and presumably be declared, it will be crucial to distinguish such activity from that which is proscribed by the particular agreement. In some instances this distinction may be difficult as the signatures of the different activities will be very

similar. This is the primary reason for the rigorous controls set up for the sampling and analysis activities.

4. What Will Sampling And Analyses Cost?

The cost of sampling and analyses is by no means trivial, particularly with the rigorous quality control measures to be enforced. Most samples will run in the neighborhood of \$1000 per analyte to be measured. Some particularly difficult (trace quantities, etc.) could run as much as a factor of ten higher. These cost projections do not include new facilities or equipment or analytical methods R&D.

The Arms Control Agreements:

A number of arms control agreements are either under active negotiation or are envisioned for the near future. Both bilateral and multi-national negotiations are or will occur. These agreements will attempt to control a wide variety of activities ranging from the production of nuclear weapons relevant materials to the destruction of current weapon stocks and the control the nuclear material thus made available.

Although the details of such agreements not yet available, certain forecasts can be made with some assurance. These predictions are summarized in Table1.

The Nuclear Non-Proliferation Treaty is not included in this discussion since only its extension is up for negotiation. However, it should be noted that the collection and analysis of environmental samples is currently being assessed by the IAEA to enhance its safeguard activities with quite positive results.

Consideration of Individual Agreements:

As the treaty (agreement) limited items or activities vary widely, it will be necessary to examine each agreement individually and in some detail.

Sampling And Analysis In Support Of A Comprehensive Test Ban Treaty-- CTBT:

The Comprehensive Test Ban Treaty (CTBT), currently under negotiation in Geneva, will attempt to eliminate nuclear testing and to put into effect a verification

	Facilities	Inspected Material	Possible Analytes	Notes
Agreement			etc.	
Comprehensive Test Ban Treaty	Nuclear test sites, could include smaller hydro test facilities.	Fission products	Isotope presence and ratios	the nature of the event and the yield need to be determined.
Dismantlement and storage facilities for Weapon Components	Pantex, Y-12, possibly Rocky Flats, Analogous Russian facilities	Pits, possibly secondaries	Pu, HEU, Be, B, T, LiD, LiH, possibly some non-nuclear material	It is important to trace the material to actual nuclear assemblies either by physical characteristics or some other method.
Cessation of Pu production. (Bilateral Protocol)	Hanford, Savannah River, possibly storage facilities. Analogous Russian facilities	Pu production reactors, Reprocessing plants	Pu, Np, U238, TBP, cladding material, shorter lived isotopic impurities	Time frame of operation will be most important. Only recent operation is proscribed.
HEU purchase transparency measures (Bilateral Protocol)	Portsmouth GDP, and Russian facilities	Russian HEU	Uranium isotopics, especially minor isotopes (233, 234 and 236)	The most important question is if the material came from a dismantled weapon.

Special Nuclear	Portsmouth,	SNM (PU, HEU and	Shorter lived	Like the Bilateral
Material Cut-off	Paducah, Oak	T)	activation and	Pu Cut-off cited
	Ridge, Savannah		fission products.	above, the
	River, Hanford, and			important question
	ICPP, Others if			will be when the
	Challenge			SNM was made.
	Inspections are			Isotopic ratios of
	involved Analogous			trace elements
	foreign facilities			could be a key.
Excess US	Y-12, Hanford,	US Pu and HEU	Isotopic ratios	IAEA already
material offered	Rocky Flats,			performs
for IAEA	perhaps others.			characterization
Safeguards				of material.

Table 1. Current and near future Nuclear Arms Control Negotiations

regime capable of detecting violations. (There is an ongoing debate as to whether some level of "hydro-nuclear" testing will be allowed. The credibility of an effective verification regime for a ban on tests yielding only a few pounds or tens of pounds of nuclear yield is dubious at best). The verification regime now being discussed begins with the detection of an anomalous seismic event and proceeds with a visit by an international team of inspectors to the site of the source of the anomalous event. The inspectors will attempt to gather sufficient evidence, by various measurements and observations, to attribute the event to a nuclear test or to some other phenomenon; e.g., earthquake or mining.

Since the verification inspections will occur sporadically and only after a triggering event, they can be considered to be analogous to the "Challenge Inspection" regime under the Chemical Weapons Convention (CWC). It has, in fact, been suggested that a CT BT inspection would be initiated by an individual State Party to the Treaty to take place on the territory of another State Party: directly analogous to the CWC procedure.

One of the tools that a CTBT inspection team will bring with them is the collection of various samples for analysis either at the inspection site or at some off-site location. Here we examine the probable effectiveness of sampling and analysis in contributing to the verification process.

An excellent reference for the following discussion is CD/NTB/WP.xxx dated 13 December 1994, entitled "On-Site Inspection for the Comprehensive Test Ban Treaty: Phenomena, Technology, OSI Examples , Costs."

The types of samples that may be collected and the proposed analytes will depend on the nature of the suspect test (underground, underwater or atmospheric), the volatility of the analytes in question, and the elapsed time between the suspect event and the inspection of the site. These considerations are summarized in Table 2 and discussed below.

Suspect Underground Events:

The most commonly accepted inspection scenario would begin with the detection of an anomalous seismic event. An international inspection team would, after some as yet undetermined delay for fact finding and negotiation, arrive in the general vicinity of the suspect site. At this time the suspect site could be hundreds of square kilometers in area. As is the case for any sampling endeavor, the most important decision is where to collect the sample. Depending on the depth of burial and other factors, (assuming a nuclear test actually took place), the exact location of the event may or may not be easily determined.

Unless an extensive and expensive statistically based sample collection protocol is to be enacted, it will be necessary to narrow the search area considerably.

Gas Sampling - Assuming that sampling locations have been determined, the first samples collected will be gas samples. In particular, inspectors will seek to determine the presence of isotopes of the noble gases Xenon (131 Xe, 133 Xe and 135 Xe), Krypton (85 Kr) and Argon 37 Ar) as these are essentially definitive for nuclear fission although not necessarily for nuclear explosives testing. Other evidence drawn from the inspection site will be needed for more definitive conclusions. The xenon and krypton isotopes are direct

Table 2. Sampling And Analysis In Support Of A CTBT

Suspect Test Venue	Sample Type	Collectab ility	Analyzabi lity	Interpreta bility	Relative Cost	Comments
Undergroun d	Gas, short lived Radioactivit y, 135Xe, 133Xe, some 131Xe	Short half- life, (9hr & 5dy), need quick response (2wk -4wk), Possibly need shallow well	β^{-} and γ emitters, analyzed by counting.	Finding these isotopes is good evidence of a nuclear explosion. No background problem.	Analysis cost is low. Collection cost could be moderate if site survey required.	Conditions need to be just right to find these isotopes. Short t _{1/2} shows recent event.
Undergroun d	Gas, Long lived 85 _{Kr,} 37 _{Ar}	Longer half- life allows for diffusion. Shallow well may be needed	Analyzed by counting. 37 Ar requires special technique for low energy X-ray.	85Kr background Finding these isotopes is good evidence of a nuclear explosion.	Analysis cost is low. Collection cost could be moderate if site survey required.	Longer t _{1/2} makes dating of event difficult. Former test sites have residual signals.
Undergroun d	Gas, Naturally occurring, CO ₂ , CH ₄ , Rn, H ₂	May be collected from shallow well.	Gases analyzed by MS.	Not definitive, look for change in flow rate. Comparative measure needed before event.	Low, may be increased if drilling required.	Normal flow disturbed by explosion. Not definitive. Not recommended
d	Environment al / vegetation	easily collected, long time after event	extensive sample preparation needed	Look for increase in trace radioactive elements, fallout background a problem	Relatively low cost, app. \$1000 per sample.	Long time needed for plant ingestion. Not definitive. Not recommended.
Suspect Test Venue	Sample Type	Collectab	Analyzabi lity	Interpreta bility	Relative Cost	Comments
Undergroun d	Cavity Debris, non- volatile fission products possibly some actinides, (if allowed)	Requires drill-back into cavity.	Analyzed by gamma ray spectromet ry / ICPMS after sample preparation	Definite for nuclear test.	Very high cost.	Large drill rig needed along with extensive site survey. Decontaminat ion needed.

Under water	Gas, short lived Radioactivit y, ¹³⁵ Xe, ¹³³ Xe, some ¹³¹ Xe.	High volume air sampler, need to find plume, Aircraft needed.	β^- and γ emitters, analyzed by counting.	Gases vented, atmospheric models needed to trace back to event site, definitive.	Moderate because of need to detect plume.	Conditions need to be just right to find these isotopes. Short t _{1/2} shows recent event.
Under water	Gas, Long lived 85Kr, Possibly some ³⁷ Ar	High volume air sampler/ aircraft needed to find plume,	Analyze by counting. 85Kr for γ ray, 37Ar for X-ray	Gases vented, atmospheric models needed, good evidence	Moderate because of need to detect plume	Significant background from previous testing.
Under water	Non volatile fission products and mutants.	Need to find plume. Grab samples usually sufficient, Boat / aircraft needed.	Need for single particle analysis.	Definitive for nuclear test	Moderate to high because of need to detect plume with boat or aircraft and need for single particle analysis Models needed for trace back	Attribution difficult or impossible. Other evidence needed to define event site.
Suspect Test Venue	Sample Type	Collectab ility	Analyzabi lity	Interpreta bility	Relative Cost	Comments
Atmospher ic / low altitude	Radioactive gases and other fission products, perhaps mutants and actinides.	High volume air sampler needed, aircraft needed.	Single particle analysis needed for non volatile fission products, etc.	Definitive for nuclear test. Must be significant over background.	Moderate to high because of need for aircraft and single particle analysis	Attribution difficult or impossible if over ocean.
Atmospher ic / low altitude	Environment al samples for fission product fallout.	Easily once surface radioactivi ty detected.	Gamma ray spectromet ry, ICPMS or single particle analysis.	Quantization needed to separate from background	Low to moderate	Only applicable if over ground.

fission products. The argon arises from the intense neutron bombardment of calcium atoms both in the device and in the soil. Depending on the concentration of the gases, the xenon and krypton isotopes can be measured by gamma ray spectrometry. The argon must be determined in a special device that can count the low energy x-ray emitted during its decay.

The detection of the xenon isotopes is particularly important because their short half-lives (131 Xe=11.92 days, 133 Xe =5.25 days and 135 Xe=9.10 hours) allow for the dating of the event to a fairly close approximation. However, if access to the site and sample collection does not occur within a month or two of the suspect event, the probability of finding these isotopes is very low.

The longer half-lives of the krypton and argon (85 Kr=10.72 years and 37 Ar=34.8 days) increases the probability of their detection even a year or so after the event. In fact, the long $t_{1/2}$ complicates the background measurement. This is especially true for the krypton where a significant background level has resulted from the previous test programs and from the reprocessing of nuclear fuel. In either case, the detected levels must be significantly above normal background if the measurements are to used for inspection purposes.

All things considered, the 37 Ar becomes the analyte of primary interest; even though this isotope is difficult to determine. The necessary analytical methodology has been developed and applied with quite good results.

The flow and distribution of naturally occurring gases such as carbon dioxide, methane, hydrogen and radon can be significantly changed as a result of an underground nuclear explosion. Similar changes could also result from other phenomena such as an earthquake. In any case, the conditions prior to the event would have to be known before conclusions could be drawn. Such samples would not be recommended.

Before going on to other sample types, some discussion should be made concerning the collection of gas samples. Since the xenon, krypton and argon are formed in the immediate vicinity of the actual explosion, they must migrate to the surface. Beyond the fracture zone, this migration is by diffusion and, depending on the geology, can take weeks or months. The sampling can be accelerated by the drilling of shallow wells or implacing penetrometers. If wells are needed, access to a drilling rig is required. Extensive drilling can be a costly and time consuming endeavor.

Environmental Samples - Environmental samples such as soil and vegetation will only show evidence of an underground nuclear explosion after a period of time long enough for the fission products, etc. to migrate through ground water and, if plants, be ingested. This can take years. Such samples would not be recommended.

Samples from the Explosion Cavity - If samples can be obtained directly from the explosion cavity, the analysis for non-volatile fission products and some longer lived actinides will be definitive. Some useful measurements can be performed with portable gamma spectrometers to determine the ratios of some of the fission fragments. This will allow the approximate dating of the event. Further analysis by mass spectrometric techniques (ICPMS or TIMS) can divulge very sensitive information about device design and may not be allowed.

However, the collection of such samples is very expensive as it requires drilling back into the explosion cavity. In the absence of evidence at the surface to pin-point the drilling site, the location of the cavity can also be expensive and time consuming. Even after the site is localized, a significant and expensive drilling capability will be needed to enter the cavity without venting radioactivity to the environment.

Based on the above discussion, it must be concluded that the analysis of samples collected at a suspect site can be definitive for an underground nuclear explosion. To some level of detectability, analyses by radiation counting can be performed at the inspection site. Lower levels of detection can be achieved in an off-site laboratory. Analyses of non volatile materials by mass spectrometry and single particle analyses must be done off site.

However, the cost of collecting such samples can be prohibitive, particularly if the event site cannot be localized by other means. A protocol for making decisions on when and how to proceed with sample collection should be agreed to before the onset of inspections.

Suspect Under Water Events:

A second possible site for clandestine nuclear testing is the open ocean (or possibly a large sea or lake). In any case, the hot gases, including the Xenon, Krypton and Argon isotopes cited above, will be vented to the atmosphere carrying with them other radioactive materials. (One possible exception to this venting is an explosion very deep under water). The remaining explosion products will rise more slowly,

cool and be, in time, dispersed by the currents and diffusion. Sample collection is therefore resolved into two parts; air sampling of the ejecta and water sampling of the retained products.

Although one would expect to see much smaller amounts of 37 Ar from under water explosions because of the lack of calcium bearing soil, the other expected products will be similar to those discussed for underground explosions. The analyses, with one exception, and interpretation of results is likewise the same. The analysis of single debris particles for explosion related isotopes will likely play a major role relative to these types of inspections.

Air Sampling - The collection of samples of ejecta will generally require aircraft deployed high volume air samplers. Since the concentration of analytes will relatively quickly drop below levels clearly distinguishable above background, due to dispersion and rain-out / fall-out, collections must be made within a week or two of the suspect event. Even then, it will probably be necessary to use good atmospheric computer models to narrow the search volume to practical limits.

Water Sampling - The products retained in the water will disperse more slowly that those in the atmosphere. One could expect to be able to collect significant samples for up to a couple of months after the suspect event. High volume water samplers will probably be used, although grab samples may be adequate if the concentration is high enough. Samplers may be deployed from either boats or aircraft (helicopter). Similar to the case of atmospheric sampling, hydrologic models may be needed to define probable search areas.

Suspect Atmospheric Events:

The discussion of sampling and analysis under this type of event is much the same as the discussion of air sampling after an under water event. This includes the expected lower concentration of 37 Ar, the utility of analyzing single debris particles and the time limits imposed by atmospheric dispersion and rain-out / fall-out.

Another aspect is added if the event takes place over ground at low altitude. In this case, a large amount of surface material can be entrained and made radioactive. Traces of this material can be detected because of its radioactivity as it falls back to the earth surface. Atmospheric models would again be used to predict the fall-out pattern for sample collection. Care must be exercised in interpreting these data so as to distinguish them from radioactivity arising from fall-out from previous atmospheric nuclear tests and from the Chernobyl accident.

The analysis of both atmospheric and water samples can be definitive for a nuclear explosion. However, care must be taken to distinguish gas sample results from background. These results could also arise from a fission event other than a nuclear explosion. The detection of non volatile fission products is more definitive but will require single particle analysis.